

Memory Commands

The memory commands control saving and loading instrument states and measurement trace data to the hard drive. To read and write trace data in GPIB format, see [CALC:MEAS:DATA](#).

MMEemory:

CATalog?

CDIRectory

COPY

DATE?

DELeTe

LOAD

| **ASCFactor**

| **BSCFactor**

| **CORRection**

| **CSARchive**

| **ENR**

| **[[:FILE]**

| **LIMit**

| **PLOsS**

| **PN**

| **SPURious**

| **OSSPur**

| **THReshold**

| **RLIMit**

| **SEGMENT**

| **STATe**

MDIRectory

MOVE

RDIRectory

STORe

| **ASCFactor**

| **BSCFactor**

| **CORRection**

| **CSARchive**

| **CSTate**

| **CITI**

| **DATA**

| **FORMat**

| **CSV:FORMat**

| **DATA**

| **CATalog**

| **EXTended**

| **SNP**

| **TAP**

| **ENR**

| **[[:FILE]**

| **LIMit**

| **PLOsS**

| **RLIMit**

| **SEGMENT**

| **SSCReen**

| **STATe**



C
笔
记

CONTENTS

CITIfile

FORMAt

CITIfile

SNP

TDR More Commands

TIME?

TRANsfer

Click on a keyword to view the command details.

Blue commands are superseded.

See Also

- [Example Programs](#)
- [Learn about Save / Recall and File Types](#)
- [Synchronizing the Analyzer and Controller](#)
- [SCPI Command Tree](#)

Specifying Path Names

The MMEM commands use the following rules to specify path names:

- The default folder is "D:\". [Learn more.](#)
- You can change the active directory using [MMEMory:CDIRectory](#).
- Specify only the file name if using the active directory.
- You can also use an absolute path name to specify the folder and file.

MMEMory:CATalog[:<char>]? [<folder>]

Applicable Models: All

(Read-only) Returns a comma-separated string of file names that are in the specified folder. If there are no files of the specified type, "NO CATALOG" is returned. [Learn about File Types.](#)

Note: If [Enable Remote Drive Access](#) is unchecked in the Remote Interface dialog, this command will return an error.

Parameters

- <char>

The type of files to list. Choose from:

- **STATe** - Instrument states (.sta)
 - **CORRection** - Calibration Data (.cal)
 - **CSARchive** - Instrument state and calibration data (.csa)
 - **CSTate** - Instrument state and link to Calibration data (.cst)
 - **[:File]**

If unspecified then ALL file types (even unknown types) are listed.

- <folder>

String - Any existing folder name. See [Specifying Path Names](#)

Examples

```
MMEM:CAT? 'lists all files from the current folder
mmemory:catalog:correction? 'D:\' 'lists .cal files from the
specified folder
```

Default

Not applicable

MMEMory:CDIRectory <folder>



Note: If **Enable Remote Drive Access** is unchecked in the Remote Interface dialog, this command will return an error.

Parameters

<folder> Any drive and folder name that already exists.
If the same level as the default path, then no punctuation is required.
MMEM:CDIR Service
If the new folder is at a different level than the default, use a slash (/) before the folder name and enclose in quotes.
`mmemory:cdirectory '/automation' 'changes default directory up or level.'`
You can use an absolute path to specify the new folder.
`mmemory:cdirectory 'C:/automation/service'`

Query Syntax MMEMory:CDIRectory? **Returns the current folder name**

Return Type String

Default See **Specifying Path Names**



MMEMory:COPY <file1>,<file2>

Applicable Models: All
(Write-only) Copies file1 to file2. Extensions must be specified.

Note: If **Enable Remote Drive Access** is unchecked in the Remote Interface dialog, this command will return an error.

Parameters

<file1> String - Name of the file to be copied. See **Specifying Path Names**
<file2> String - Name of the file to be created from file1.

Examples `MMEM:COPY 'MyFile.cst', 'YourFile.cst'`

Query Syntax Not applicable

Default Not applicable

MMEMory:DATE? <fileName>

Applicable Models: All
(Read-only) Returns the (year, month, day) that the specified file was last saved.
To query the last date and time a cal set was modified, use **CSET DATE?** and **CSET:TIME?**

See Also

MMEM:TIME?

Parameters

<fileName> String - File name. See **Specifying Path Names**

Example `MMEM:DATE? "myFile.txt"`
Returns
`+2013,+4,+12`
`mmemory:date? "D:\Calset_18.pcs"`

Return Type Comma-separated integers

Default Not applicable

MMEMory:DELeTe <file>

Applicable Models: All

(Write-only) Deletes file. Extensions must be specified.

Note: If **Enable Remote Drive Access** is unchecked in the Remote Interface dialog, this command will return an error.

Parameters

<file> String - Name of the file to be deleted. See [Specifying Path Names](#)

Examples `MMEM:DEL 'MyFile.cst'`

Query Syntax Not applicable

Default Not applicable

MMEMory:LOAD[:<char>] <file>

Applicable Models: All

(Write-only) Loads the specified file. [Learn about File Types](#)

Parameters

<char> The type of file to load. Choose from:

- **ASCFactor**
- **BSCFactor**
- **STATe** - Instrument states (.sta)
- **CORRection** - Calibration Data (.cal)
- **CSARchive** - Instrument state and calibration data (.csa)
- **CSTate** - Instrument state and link to Calibration data (.cst)
- **ENR** - Excess Noise Source data ([Noise Figure App only](#))
- **SEGMENT**
- **[:File]**
- **PLOSs**
- When <char> is **ENR**, then include **CAL**, - See example below.
- *.snp files CAN be recalled to the VNA although no <char> is used. See example below.

If <char> is unspecified, the extension must be included in the filename.

If an extension is specified in <file> that does not agree with <char> then no action is taken.

<file> String - Name of the file to be loaded. See [Specifying Path Names](#)

Examples

```
MMEM:LOAD 'MyFile.cst'
mmemory:load:state 'MyInstState'
MMEM:LOAD:ENR CAL, "D:/data/calset/346C_16500.enr"
MMEM:LOAD "MyFile.s2p"
```

Query Syntax Not applicable



C
笔
记

MMEMory:LOAD:LIMit <file>

Applicable Models: All

(Write-only) Load limit test data of the active trace of the active channel from a CSV file.

Parameters

<file> A file path by string format.
The CSV file shall have header lines and a title row as follows.
"# E5080 Limit Test"
"# Revision: 1.00"
TYPE,BEGIN STIMULUS,END STIMULUS,BEGIN RESPONSE,END RESPONSE

Examples MMEM:LOAD:LIM 'MyFile.csv'

Query Syntax Not applicable

Default Not applicable



MMEMory:LOAD:PN:SPURious:OSSPur <file>

Applicable Models: N522xB, N524xB with Phase Noise Option S93031xB

(Write-only) Load user specified spurious frequency list of the active trace of the active channel.

Parameters

<file> String - Name of the user specified spurious frequency list. See [Specifying Path Names](#)

Examples MMEM:LOAD:PN:SPUR:OSSP 'MyFile.csv'
mmemory:load:pn:spurious:osspur 'D:/MyFile.csv'

Query Syntax Not applicable

Default Not applicable

MMEMory:LOAD:PN:SPURious:THReshold <file>

Applicable Models: N522xB, N524xB with Phase Noise Option S93031xB

(Write-only) Load the threshold table of the active trace of the active channel.

Parameters

<file> String - Name of the threshold table. See [Specifying Path Names](#)

Examples MMEM:LOAD:PN:SPUR:THR 'MyFile.csv'
mmemory:load:pn:spurious:threshold 'D:/MyFile.csv'

Query Syntax Not applicable

Default Not applicable

MMEMory:LOAD:RLIMit <file>

Applicable Models: All

(Write-only) Load ripple limit test data of the active trace of the active channel from a CSV file.

The CSV file shall have header lines and a title row as follows.

"# E5080 Ripple Limit Test"

"# Revision: 1.00"

TYPE,BEGIN STIMULUS,END STIMULUS,MAX RIPPLE

Examples `MMEM:LOAD:RLIM 'MyFile.csv'`

Query Syntax Not Applicable

Default Not Applicable



C
笔
记

MMEMory:MDIRectory <folder>

Applicable Models: All

(Write-only) Makes a folder.

Note: If **Enable Remote Drive Access** is unchecked in the Remote Interface dialog, this command will return an error.

Parameters

<folder> String - Name of the folder to make. See [Specifying Path Names](#)

Examples `MMEM:MDIR 'MyFolder'`
`mmemory:mdirectory 'D:/NewFolder'`

Query Syntax Not applicable

Default Not applicable

MMEMory:MOVE <file1>,<file2>

Applicable Models: All

(Write-only) Renames <file1> to <file2>. File extensions must be specified.

Parameters

<file1> String - Name of the file to be renamed. See [Specifying Path Names](#)

<file2> String - Name of the new file.

Examples `MMEM:MOVE 'MyFile.cst', 'YourFile.cst'`

Query Syntax Not applicable

Default Not applicable

MMEMory:RDIRectory <folder>

Applicable Models: All

(Write-only) Removes the specified folder.

Note: If **Enable Remote Drive Access** is unchecked in the Remote Interface dialog, this command will return an error.

Parameters

<folder> String - Name of the folder to remove. See [Specifying Path Names](#)

Query Syntax Not applicable

Default Not applicable

MMEMory:STORe[:<char>] <file>

Applicable Models: All

(Write-only) Stores the specified file (.sta, .cal, .cst, .csa, .snp, s2px).

Learn about [saving SNP files on the VNA](#).

Learn about [saving S2Px files on the VNA](#).

To save other data files, use **MMEM:STOR:DATA**.

To save ENR files, use **MMEMory:STORe:ENR**

Parameters

<char> Optional argument. The type of file to store. Choose from:

- **ASCFactor**
- **BSCFactor**
- **CORRection** - Calibration Data (.cal)
- **CSARchive** - Instrument state and calibration data (.csa)
- **CSTate** - Instrument state and link to Calibration data (.cst)
- **CSV:FORMat**
- **ENR**
- **[:File]**
- **PLOsS**
- **SEGMENT**
- **STATe** - Instrument states (.sta)
- **STATe:TRACe**
- **TRACe**

No <char> is specified for s1p, s2p, s2px and so forth.

Include either <char> or the file extension. If both <char> and the extension are specified, they must agree or an error is returned and no action is taken. See examples below.

[Learn about File Types](#)

<file> String - Name of any valid file that does not already exist. See [Specifying Path Names](#)

Examples **MMEM:STOR:STAT** 'myState'
mmemory:store 'c:/bin/myState.sta'
MMEM:STOR 'MyData.S2P'

Query Syntax Not applicable

Default Not applicable

MEMory:STORe:CATalog? <legacy>

Applicable Models: All

(Read only) Returns a list of all available file types for the current measurement class. Legacy file type names are used in the **MMEM:STOR:DATA** command. New file type names are used in the **MMEM:STOR:DATA:EXTended** command.



Legacy: (integer) Choose item.
0 – Returns list of new file type names
1 – Returns list of legacy file type names

Examples

MMEM:STORE:DATA:CAT? 0
Returns “CSV Trace (*.csv);Citifile Trace (*.cti);MDIF Trace (*.mdf);PRN Trace (*.prn);S1P Network (*.s1p);S2P Network (*.s2p);S3P Network (*.s3p);S4P Network (*.s4p)”

MMEM:STORE:DATA:CAT? 1
Returns “PRN Trace Data (*.prn);Citifile Data Data (Real,Imag) (*.cti);Citifile Formatted Data (*.cti);CSV Formatted Data (*.csv);MDIF Data (*.mdf);Trace (*.s1p);Trace (*.s2p);Trace (*.s3p);Trace (*.s4p)”

Default Not applicable



MMEMory:STORe:CITifile:DATA <filename> - Superseded

Applicable Models: All
This command is replaced with **MMEMory:STORe:DATA**.
(Write only) Saves UNFORMATTED trace data to .cti file. [Learn more.](#)

Parameters

<filename> Any path that already exists with filename.
If the same level as the default, then no path is required.
MMEM:STOR:CIT:DATA 'MYFile.cti'
Of you can specify an absolute path and filename:
mmemory:store:citifile:data "D:\myFile.cti"

Query Syntax Not Applicable

Default See [Specifying Path Names](#)

MMEMory:STORe:CITifile:FORMat <filename> - Superseded

Applicable Models: All
This command is replaced with **MMEMory:STORe:DATA**.
(Write only) Saves FORMATTED trace data to .cti file. [Learn more.](#)

Parameters

<filename> Any path that already exists with filename.
If the same level, then no path is required
MMEM:STOR:CIT:FORM 'MYFile.cti'
Of you can specify an absolute path and filename:
mmemory:store:citifile:format "D:\myFile.cti"

Query Syntax Not Applicable

Default See [Specifying Path Names](#)

MMEMory:STORe:DATA <filename>,<type>,<scope>,<format>,<selector> - Superseded

This command is replaced with **MMEMory:STORe:DATA:EXTended**.

Notes:

To save snp files for standard channels (only), use **CALC:MEAS:Data:SNP:PORTs:SAVE**

To save state and calibration files, use **MMEM:STORe**

This command replaces the following:

- **MMEMory:STORe:CITifile:DATA**
- **MMEMory:STORe:CITifile:FORMat**
- **MMEMory:STORe:TRACe:FORMat:CITifile**
- **MMEMory:STORe:TRACe:CONTent:CITifile**



C
笔
记

Parameters

- <filename>** (String) Name and extension of the file to which data will be saved. If the extension does not agree with the file type, an error is NOT returned but the data may NOT be what you expect.
- [See rules for specifying a filename.](#)
- <type>** (String) File type to save. Choose from:
- "PRN Trace Data"** - *.prn data. [Learn more.](#)
 - "Citifile Data Data"** - unformatted *.cti data. [Learn more.](#)
 - "Citifile Formatted Data"** - formatted *.cti data.
 - "CSV Formatted Data"** - formatted *.csv data. [Learn more.](#)
 - "MDIF Data"** - *.mdf data. [Learn more.](#)
 - "GCA Sweep Data"** - Gain compression data. [Learn more.](#)
 - "GCX Sweep Data"** - Gain compression data. [Learn more.](#)
 - "IMD Sweep Data"** - Swept IMD data. [Learn more.](#)
- <scope>** (String) How much data to save. Choose from:
- "Trace"** - only the specified measurement number is saved.
 - "Displayed"** - all displayed measurements are saved.
 - "Channel"** - all measurements that are in the channel in which the selected measurement reside are saved.
 - "Auto"**
 - For all Standard Meas Class (S-parameter) channels:
 - When correction is OFF, the specified trace is saved.
 - When correction is ON, all corrected parameters associated with the calibrated ports in the Cal Set are saved.
 - For all other channels:
 - When correction is OFF or ON, the specified trace is saved.
- <format>** The format in which data is saved. Choose from:
- "Displayed"** - the format is the same as that in which it is displayed on the VNA screen.
 - "RI"** - Real / Imaginary
 - "MA"** - Magnitude / Angle
 - "DB"** - LogMag / Degrees
- <selector>** (Integer) Choose from:

The following are **valid parameter combinations** for ALL measurement classes:

Parameters			
<type> (String)	<scope> (String)	<format> (String)	<selector> (Numeric)
"PRN Trace Data"	"Trace"	"Displayed"	Measurement number
Example: <code>MMEemory:STORe:DATA "myData.prn","PRN Trace Data","Trace","Displayed",2</code>			
"Citifile Data Data"	"Trace" or "Auto" or "Channel"	"RI"	Measurement number
	"Displayed"	"RI"	-1
Example: <code>MMEemory:STORe:DATA "myData.cti","Citifile Data Data","AUTO","RI",3</code>			
"Citifile Formatted Data"	"Trace" or "Auto"	"RI" or "MA" or "DB"	Measurement number
	"Channel"	"RI" or "MA" or "DB" or "Displayed"	Measurement number
	"Displayed"	"RI" or "MA" or "DB" or "Displayed"	-1
Example: <code>MMEemory:STORe:DATA "myData.cti","Citifile Formatted Data","AUTO","MA",3</code>			
"CSV Formatted Data"	"Trace" or "Auto" or "Channel"	"RI" or "MA" or "DB" or "Displayed"	Measurement number
	"Displayed"	"RI" or "MA" or "DB"	-1
Example: <code>MMEemory:STORe:DATA "myData.csv","CSV Formatted Data","displayed","RI",-1</code>			
"MDIF Data"	"Trace" or "Auto"	"RI" or "Displayed" or "Channel"	Measurement number
	"Displayed"	"RI" or "Displayed"	-1
Example: <code>MMEemory:STORe:DATA "myData.mdf","MDIF Data","displayed","displayed",-1</code>			

The following parameter combinations save *.csv files in specific formats for GCA, GCX, and Swept IMD classes:

Parameters			
<type> (String)	<scope> (String)	<format> (String)	<selector> (Numeric)
"GCA Sweep Data"	"Auto"	"DB"	GCA channel number
Example: <code>MMEemory:STORe:DATA "myData.csv","gca sweep data","displayed","displayed",-1</code>			
"GCX Sweep Data"	"Auto"	"DB"	GCX channel number
Example: <code>MMEemory:STORe:DATA "myData.csv","gcx sweep data","displayed","displayed",-1</code>			

Query Syntax	Not applicable
Default	Not applicable

MMEMory:STORe:DATA:EXTended <filename>,<type>,<scope>,<format>,<selector>

Applicable Models: All

(Write-only) Stores trace data to the following file types: PRN Trace, Citifile Trace, CSV Trace, MDIF Trace. in addition to application specific file types.
The processing stage of the data can be selected with **MMEMory:STORe:TAP**. Application specific file types will not be affected by the processing stage selection and can only save "Corrected" data.

Parameters

- <filename>

(String) Name and extension of the file to which data will be saved. If the extension does not agree with the file type, an error is NOT returned but the data may NOT be what you expect.
[See rules for specifying a filename.](#)
- <type>

(String) File type to save. Choose from:
"PRN Trace" - *.prn data. [Learn more.](#)
"Citifile Trace" - unformatted *.cti data. [Learn more.](#)
"CSV Trace" - formatted *.csv data. [Learn more.](#)
"MDIF Trace" - *.mdf data. [Learn more.](#)
Application
"CSV AHP"
"CSV GCA" - Gain compression data. [Learn more.](#)
"CSV GCX" - Gain compression data. [Learn more.](#)
"CSV IMD" - Swept IMD data. [Learn more.](#)
"CSV Mixer" - SMC/VMC data
"NCO Noise Correlation" – Noise Correlation data
"S2P Noise Parameters" – Noise parameter data
"S2PX Mixer" – SMC/VMC data
"XParam" – Active Hot Parameter data
- <scope>

(String) How much data to save. Choose from:
"Single" - only the specified measurement number is saved.
"Displayed" - all displayed measurements are saved.
"Channel" - all measurements that are in the channel in which the selected measurement reside are saved.
"Auto"
For all Standard Meas Class (S-parameter) channels:
 - When correction is OFF, the specified trace is saved.
 - When correction is ON, all corrected parameters associated with the calibrated ports in the Cal Set are saved.For all other channels:
 - When correction is OFF or ON, the specified trace is saved.



PXIe VNA Help

[Click here to see this page in full context](#)

Citifile Trace (*.cti)	Formatted Corrected	Auto Single Channel Displayed	DB MA RI Displayed
CSV Trace (*.csv)	Formatted Corrected	Auto Single Channel Displayed	DB MA RI Displayed
MDIF Trace (*.mdif)	Formatted Corrected	Auto Single Channel Displayed	RI Displayed
PRN Trace (*.pm)	Formatted Corrected	Single	Displayed
CSV IMD (*.csv)	Corrected	Channel	DB
CSV Mixer (*.csv)	Corrected	Channel	DB
S2PX Mixer (*.s2px)	Corrected	Channel	Displayed
CSV GCA (*.csv)	Corrected	Channel	DB
CSV GCX (*.csv)	Corrected	Channel	DB
NCO Noise Correlation (*.nco)	Corrected	Channel	Displayed
S2P Noise Parameters (*.s2p)	Corrected	Channel	DB MA RI
CSV AHP (*.csv)	Corrected	Channel	DB
XParam (*.xnp)	Corrected	Channel	RI

C
笔
记

<format> The format in which data is saved. Choose from:

"Displayed" - the format is the same as that in which it is displayed on the VNA screen.

"RI" - Real / Imaginary

"MA" - Magnitude / Angle

"DB" - LogMag / Degrees

<selector> (Integer) Choose from:

-1 Use when <scope> = "Displayed" (does NOT require a selected trace).

<measurement number> Use for all other <scope> selections. Use **Calc:Par:MNUM?** to read the measurement number of the selected trace.

Examples **MMEM:STORE:DATA:TAP "Corrected"**
MMEM:STORE:DATA:EXT "myData.cti", "citifile trace", "single", "db", 1"

Query Syntax Not applicable

Return Type Depends on **MMEM:STORE:DATA:TAP**

Default Not applicable

MMEMory:STORE:DATA:SNP <filename>,<ports>,<format>,<touchstoneversion>

Applicable Models: All

(Write-only) Saves S-Parameter data for the specified ports.

PXIe VNA Help

[Click here to see this page in full context](#)

- [Supports reordering or ports.](#)
- Uses the FAST SnP save routine if the following conditions are met:
 - A valid correction is applied
 - Current tap is "Corrected"
 - **SENS:CORR:CACH:MODE** is on
- Automatically downgrades correction for FAST SnP file saves when provided port list is a subset of calibrated ports. Learn more about [SNP data](#).
- Data that is not available is zero-filled.
- For sweeps with a large number of data points, always follow this command with *OPC? Learn more.
- Supersedes **CALCulate:MEASure:DATA:SNP:PORTs:SAVE**.

Parameters

<filename> (String) Name and extension of the file to which data will be saved. If the extension does not agree with the file type, an error is NOT returned but the data may NOT be what you expect.

[See rules for specifying a filename.](#)

<port> (String) Comma delimited list of port numbers. Supports port reordering.

<format> The format in which data is saved. Choose from:

"AUTO" - Auto.

"RI" - Real / Imaginary

"MA" - Magnitude / Angle

"DB" - LogMag / Degrees

<touchstone version> (Integer) Only supports 1.1 as of now.

Examples **MMEM:STORE:DATA:TAP "Formatted"**

MMEM:STOR:DATA:SNP "myData.s2p", "2,1", "ri", 1.1

Query Syntax Not applicable

Return Type Not applicable

Default Not applicable



C
笔
记

MMEMory:STORe:DATA:TAP <tap>**Applicable Models:** All

(Read and Write) Specifies where in the data access map the data is saved from. To be used in conjunction with **MMEM:STORE:DATA:EXTended**. This command only applies to the following file types: PRN Trace, Citifile Trace, CSV Trace, MDIF Trace, and SnP Network, but not application specific file types. [Learn more.](#)

NOTE: The tap setting associated with this command is also shared with the GUI in the system registry. For example, if you set the tap using this command but proceed to use the GUI and save a file as a different tap, the shared tap setting will be changed. Users may use the query syntax of this command to see what the current tap is. When a tap is selected and a file is saved using the SCPI save command, it will validate the tap to see if it's valid for the specified file type. If it's not valid, a valid tap is chosen for the save. For example, if a user chooses "Revision 2023" and saves a non-snp file, the file saved may be "Corrected" or "Formatted" because non-snp SnP files do not have the option of "Revision 2023".

Parameters

<tap> (String) Choose from:
 "Corrected" – Saves from Tap 1
 "Formatted" – Saves from Tap 2 (if <format> = "RI", then data will NOT include smoothing)
 "Revision 2023" – Special legacy SnP tap. This operation preserves legacy operation from code shipping in 2023 for customers requiring backwards compatibility.

Query Syntax `MMEM:STOR:ENR:CAL?`

Return Type String

Default Not applicable

MMEMory:STORe:ENR CAL, <file>

Applicable Models: All
(Write-only) Stores an **ENR** (Excess Noise Source) data. (Noise Figure App only)
To set and read ENR data, use **SENS:CORR:ENR:CAL:TABLE:DATA**.

Parameters

<file> String - Name of any valid file that is not already in existence. See [Specifying Path Names](#)

Examples `MMEM:STOR:ENR CAL, "C:/data/calset/346C_16500.enr"`

Query Syntax Not applicable

Default Not applicable



MMEMory:STORe:LIMit <file>

Applicable Models: All
(Write-only) Saves limit test data of the active trace of the active channel into a CSV file.

Parameters

<file> A file path by string format.
The CSV file shall have header lines and a title row as follows.
"# VNA Limit Test"
"# Revision: 1.00"
TYPE,BEGIN STIMULUS,END STIMULUS,BEGIN RESPONSE,END RESPONSE

Examples `MMEM:STOR:LIM 'MyFile.csv'`

Query Syntax Not Applicable

Default Not Applicable

MMEMory:STORe:RLIMit <file>

Applicable Models: All
(Write-only) Saves ripple limit test data of the active trace of the active channel into a CSV file.

Parameters

<file> A file path by string format.
The CSV file shall have header lines and a title row as follows.
"# VNA Ripple Limit Test"
"# Revision: 1.00"
TYPE,BEGIN STIMULUS,END STIMULUS,MAX RIPPLE

Examples `MMEM:STOR:RLIM 'MyFile.csv'`

MMEMory:STORe:SSCReen <file>

Applicable Models: All

(Write-only) Stores the specified file as a bitmap file (.bmp).

Parameters

<file> String - Name of any valid file that does not already exist. See [Specifying Path Names](#)

Examples `MMEM:STOR:SSCR 'myState'`
`mmemory:store:sscreen 'c:/bin/myState.bmp'`

Query Syntax Not applicable

Default Not applicable



MMEMory:STORe:TRACe:FORMat:CITifile <char> - **Superseded**

Applicable Models: All

This command is replaced with [MMEMory:STORe:DATA](#).

(Read-Write) Specifies the format of subsequent citifile save statements.

Parameters

<char> Format in which the citifile will be saved with subsequent [MMEMory:STORe:CIT:FORMat](#) statements. Choose from:
MA - Linear Magnitude / degrees
DB - Log Magnitude / degrees
RI - Real / Imaginary
AUTO - Format in which the trace is already displayed. If other than Log Mag, Linear Magnitude, or Real/Imag, then the format will be in Real/Imag.
DISP - Displayed format.

Examples `MMEM:STOR:TRAC:FORM:CIT MA`

Query Syntax `MMEMory:STORe:TRACe:FORMat:CITifile?`

Return Type Character

Default Auto

MMEMory:STORe:TRACe:CONTents:CITifile <char> - **Superseded**

Applicable Models: All

This command is replaced with [MMEMory:STORe:DATA](#).

(Read-Write) Specifies the contents of subsequent citifile save statements. (See [Data Define Saves](#))

Parameters

<char> Choose from:
SING - Single trace
DISP - All displayed traces

Query Syntax	MMEMory:STORe:TRACe:CONTents?
Return Type	Character
Default	Auto

MMEMory:STORe:TRACe:FORMat:SNP <char>

Applicable Models: All
(Read-Write) Specifies the format of subsequent .s1p, .s2p, .s3p; s4p save statements. [Learn more](#).
To save SNP data, use [CALC:MEAS:DATA:SNP:PORTs:SAVE](#)

Parameters

- <char> Choose from:
- MA** - Linear Magnitude / degrees
 - DB** - Log Magnitude / degrees
 - RI** - Real / Imaginary
 - AUTO** - data is output in currently selected trace format. If other than LogMag, LinMag, or Real/Imag, then output is in Real/Imag.

Examples `MMEM:STOR:TRAC:FORM:SNP MA`

Query Syntax	MMEMory:STORe:TRACe:FORMat:SNP?
Return Type	Character
Default	Auto'

MMEMory:TIME? <fileName>

Applicable Models: All
(Read-only) Returns the (hour, minute, second) that the specified file was last saved. The time is returned in local time as setup in the VNA operating system.
To query the last date and time a cal set was modified, use [CSET DATE?](#) and [CSET:TIME?](#)

See Also
[MMEM:DATE?](#)

Parameters

<fileName> String - File name. See [Specifying Path Names](#)

Example `MMEM:TIME? "myFile.txt"`
`'returns`
`+12,+34,+12`
`mmemory:time? "D:\Calset_18.pcs"`
`'returns`
`+12,+34,+12`

Return Type	Comma-separated integers
Default	Not applicable



Applicable Models: All

(Read-Write) Transfers data between the VNA and an external controller. Other MMEM commands transfer data between the VNA application and the VNA hard drive. If <fileName> already exists, it will be overwritten.

To read **trace data** from the VNA in block format, use **CALC:MEAS:DATA**.

Note: If **Enable Remote Drive Access** is unchecked in the Remote Interface dialog, this command will return an error.

Parameters

<fileName> String - File name. See [Specifying Path Names](#)

<dataBlock> **Block Data** - The contents of the file.

The data block is a block of binary data. Use the following syntax:

#<num_digits><byte count><data bytes><NL><END>

where:

<num_digits> specifies how many digits are contained in <byte_count>

<byte_count> specifies how many data bytes will follow in <data bytes>

Example:

#210ABCDE+WXYZ<nl><end>

Where:

- always sent before definite block data

2 - specifies that the byte count is two digits (2)

10 - specifies the number of data bytes that will follow, not counting <NL><END>

ABCDE+WXYZ - 10 digits of data

<NL><END> - always sent at the end of block data

Example [See example program](#)

Query Syntax MMEMory:TRANsfer? <fileName>

Reads block data from the specified file location.

Default Not applicable

